

Installing EZCap 282 on Windows 10

How to Install EZCap 282:



Recognized as an "IT9910 Capture Filter (HD)" device

1. You must get drivers – to get the drivers – google and install the Hauppauge Capture software.
 - a. Download Hauppauge Capture
 - b. With the EZCap 282 installed, run in the installer
 - i. This will recognize the chipset and Hauppauge will think it is a “Hauppauge HD-PVR Rocket” device and install the application and drivers
 - ii. Note: when you run the Hauppauge application it will not recognize your device as the PVR Rocket drivers are not associated with EZCap 282 (i.e. the IT9910 Capture Filter (HD))
2. Associate the Hauppauge driver s in Device Manager
 - a. you must assign the drivers to the EZCapture device which shows up as an unknown IT9910 Capture Filter (HD) device - use the “Sound, video and game controllers” section to add drivers for a IT9910 Grabber Device (HD) using (Audio USB Generic)
3. Goto the Hauppauge drivers location and use the HCW9910HD_64 driver pack.
 - a. Under “C:\Program Files (x86)\Hauppauge\Capture\Win10 Drivers” you will find the Win 10 64 bit driver pack “HCW9910HD_64”
 - b. Associate the drivers and you are ready to find the device in video capture applications like Hauppauge Capture, OBS Studio, etc.
4. Enjoy!